

Package ‘ao’

June 20, 2024

Title Alternating Optimization

Version 1.0.0

Description Alternating optimization is an iterative procedure that optimizes a function by alternately performing restricted optimization over individual parameter subsets. Instead of tackling joint optimization directly, it breaks the problem down into simpler sub-problems. This approach can make optimization feasible when joint optimization is too difficult.

URL <https://loelschlaeger.de/ao/>, <https://github.com/loelschlaeger/ao/>

BugReports <https://github.com/loelschlaeger/ao/issues>

License GPL-3

Encoding UTF-8

RoxygenNote 7.3.1

Imports checkmate, cli, oeli (>= 0.5.2), R6, stats, utils

Suggests ggplot2, knitr, rmarkdown, testthat (>= 3.0.0)

Config/testthat.edition 3

VignetteBuilder knitr

Depends R (>= 4.0.0), optimizeR (>= 1.1.1)

NeedsCompilation no

Author Lennart Oelschläger [aut, cre]
(<<https://orcid.org/0000-0001-5421-9313>>),
Siddhartha Chib [ctb]

Maintainer Lennart Oelschläger <oelschlaeger.lennart@gmail.com>

Repository CRAN

Date/Publication 2024-06-20 13:20:02 UTC

Contents

ao	2
ao_input_check	5
Procedure	6

Index**14**

ao	<i>Alternating Optimization</i>
----	---------------------------------

Description

Alternating optimization is an iterative procedure for optimizing a real-valued function jointly over all its parameters by alternating restricted optimization over parameter partitions.

Usage

```
ao(
  f,
  initial,
  target = NULL,
  npar = NULL,
  gradient = NULL,
  ...,
  partition = "sequential",
  new_block_probability = 0.3,
  minimum_block_number = 2,
  minimize = TRUE,
  lower = -Inf,
  upper = Inf,
  iteration_limit = Inf,
  seconds_limit = Inf,
  tolerance_value = 1e-06,
  tolerance_parameter = 1e-06,
  tolerance_parameter_norm = function(x, y) sqrt(sum((x - y)^2)),
  base_optimizer = Optimizer$new("stats::optim", method = "L-BFGS-B"),
  verbose = FALSE
)
```

Arguments

f	(function) A function to be optimized, returning a single numeric value.
	The first argument of f should be a numeric of the same length as initial , followed by any other arguments specified by the ... argument.
	If f is to be optimized over an argument other than the first, or more than one argument, this has to be specified via the target argument.
initial	(numeric()) The starting parameter values for the target argument(s).
target	(character() or NULL) The name(s) of the argument(s) over which f gets optimized. This can only be numeric arguments. Can be NULL (default), then it is the first argument of f .

npar	(integer()) The length of the target argument(s). Must be specified if more than two target arguments are specified via the target argument. Can be NULL if there is only one target argument, in which case npar is set to be length(initial).
gradient	(function or NULL) A function that returns the gradient of f. The function call of gradient must be identical to f. Can be NULL, in which case a finite-difference approximation will be used.
...	Additional arguments to be passed to f (and gradient).
partition	(character(1) or list()) Defines the parameter partition, and can be either <ul style="list-style-type: none"> • "sequential" for treating each parameter separately, • "random" for a random partition in each iteration, • "none" for no partition (which is equivalent to joint optimization), • or a list of vectors of parameter indices, specifying a custom partition for the alternating optimization process.
new_block_probability	(numeric(1)) Only relevant if partition = "random". The probability for a new parameter block when creating a random partitions. Values close to 0 result in larger parameter blocks, values close to 1 result in smaller parameter blocks.
minimum_block_number	(integer(1)) Only relevant if partition = "random". The minimum number of blocks in random partitions.
minimize	(logical(1)) Whether to minimize during the alternating optimization process. If FALSE, maximization is performed.
lower	(numeric()) Optionally lower parameter bounds.
upper	(numeric()) Optionally upper parameter bounds.
iteration_limit	(integer(1) or Inf) The maximum number of iterations through the parameter partition before the alternating optimization process is terminated. Can also be Inf for no iteration limit.
seconds_limit	(numeric(1)) The time limit in seconds before the alternating optimization process is terminated. Can also be Inf for no time limit. Note that this stopping criteria is only checked <i>after</i> a sub-problem is solved and not <i>within</i> solving a sub-problem, so the actual process time can exceed this limit.

tolerance_value
 (numeric(1))
 A non-negative tolerance value. The alternating optimization terminates if the absolute difference between the current function value and the one from the last iteration is smaller than `tolerance_value`. Can be 0 for no value threshold.

tolerance_parameter
 (numeric(1))
 A non-negative tolerance value. The alternating optimization terminates if the distance between the current estimate and the one from the last iteration is smaller than `tolerance_parameter`. Can be 0 for no parameter threshold. By default, the distance is measured using the euclidean norm, but another norm can be specified via the `tolerance_parameter_norm` field.

tolerance_parameter_norm
 (function)
 The norm that measures the distance between the current estimate and the one from the last iteration. If the distance is smaller than `tolerance_parameter`, the procedure is terminated. It must be of the form `function(x, y)` for two vector inputs `x` and `y`, and return a single numeric value. By default, the euclidean norm `function(x, y) sqrt(sum((x - y)^2))` is used.

base_optimizer (Optimizer)
 An Optimizer object, which can be created via [Optimizer](#). It numerically solves the sub-problems.
 By default, the [optim](#) optimizer is used. If another optimizer is specified, the arguments `gradient`, `lower`, and `upper` are ignored.

verbose (logical(1))
 Whether to print tracing details during the alternating optimization process.

Value

A list with the following elements:

- `estimate` is the parameter vector at termination.
- `value` is the function value at termination.
- `details` is a data.frame with full information about the procedure: For each iteration (column `iteration`) it contains the function value (column `value`), parameter values (columns starting with `p` followed by the parameter index), the active parameter block (columns starting with `b` followed by the parameter index, where 1 stands for a parameter contained in the active parameter block and 0 if not), computation times in seconds (column `seconds`), and a code that summarizes whether the update got accepted (column `update_code`, where 0 stands for an accepted update, 1 for a rejected update due to an error when solving the sub-problem, and 2 for a rejected update because it did not improve the function value).
- `seconds` is the overall computation time in seconds.
- `stopping_reason` is a message why the procedure has terminated.

Examples

```
# Example 1: Minimization of Himmelblau's function -----
```

```

himmelblau <- function(x) (x[1]^2 + x[2] - 11)^2 + (x[1] + x[2]^2 - 7)^2
ao(f = himmelblau, initial = c(0, 0))

# Example 2: Maximization of 2-class Gaussian mixture log-likelihood -----

# target arguments:
# - class means mu (2, unrestricted)
# - class standard deviations sd (2, must be non-negative)
# - class proportion lambda (only 1 for identification, must be in [0, 1])

normal_mixture_llk <- function(mu, sd, lambda, data) {
  c1 <- lambda * dnorm(data, mu[1], sd[1])
  c2 <- (1 - lambda) * dnorm(data, mu[2], sd[2])
  sum(log(c1 + c2))
}

ao(
  f = normal_mixture_llk,
  initial = c(2, 4, 1, 1, 0.5),
  target = c("mu", "sd", "lambda"),
  npar = c(2, 2, 1),
  data = datasets::faithful$eruptions,
  partition = "random",
  minimize = FALSE,
  lower = c(-Inf, -Inf, 0, 0, 0),
  upper = c(Inf, Inf, Inf, Inf, 1)
)

```

ao_input_check*Input checks***Description**

This helper function checks the inputs for the [ao](#) function.

Usage

```

ao_input_check(
  argument_name,
  check_result,
  error_message = check_result,
  prefix = "Input {.var {argument_name}} is bad:"
)

```

Arguments

`argument_name` (character(1))

The name of the argument that is checked.

check_result	(logical(1)) TRUE if the check was successful.
error_message	(character(1)) An error message to be printed.
prefix	(character(1)) A prefix before the error message.

Value

Either throws an error, or invisible TRUE.

Procedure

*Procedure Object***Description**

This object specifies alternating optimization procedure.

Active bindings

npar (integer(1))	The length of the target argument.
partition (character(1) or list())	Defines the parameter partition, and can be either <ul style="list-style-type: none"> • "sequential" for treating each parameter separately, • "random" for a random partition in each iteration, • "none" for no partition (which is equivalent to joint optimization), • or a list of vectors of parameter indices, specifying a custom partition for the alternating optimization process.
new_block_probability (numeric(1))	Only relevant if <code>partition = "random"</code> . The probability for a new parameter block when creating a random partitions. Values close to 0 result in larger parameter blocks, values close to 1 result in smaller parameter blocks.
minimum_block_number (integer(1))	Only relevant if <code>partition = "random"</code> . The minimum number of blocks in random partitions.
verbose (logical(1))	Whether to print tracing details during the alternating optimization process.
minimize (logical(1))	Whether to minimize during the alternating optimization process. If FALSE, maximization is performed.
iteration_limit (integer(1) or Inf)	The maximum number of iterations through the parameter partition before the alternating optimization process is terminated. Can also be Inf for no iteration limit.

`seconds_limit (numeric(1))`

The time limit in seconds before the alternating optimization process is terminated. Can also be Inf for no time limit. Note that this stopping criteria is only checked *after* a sub-problem is solved and not *within* solving a sub-problem, so the actual process time can exceed this limit.

`tolerance_value (numeric(1))`

A non-negative tolerance value. The alternating optimization terminates if the absolute difference between the current function value and the one from the last iteration is smaller than `tolerance_value`. Can be 0 for no value threshold.

`tolerance_parameter (numeric(1))`

A non-negative tolerance value. The alternating optimization terminates if the distance between the current estimate and the one from the last iteration is smaller than `tolerance_parameter`. Can be 0 for no parameter threshold. By default, the distance is measured using the euclidean norm, but another norm can be specified via the `tolerance_parameter_norm` field.

`tolerance_parameter_norm (function)`

The norm that measures the distance between the current estimate and the one from the last iteration. If the distance is smaller than `tolerance_parameter`, the procedure is terminated. It must be of the form `function(x, y)` for two vector inputs `x` and `y`, and return a single numeric value. By default, the euclidean norm `function(x, y) sqrt(sum((x - y)^2))` is used.

`iteration (integer(1))`

The current iteration number.

`block (integer())`

The currently active parameter block, represented as parameter indices.

`output (list(), read-only)`

The output of the alternating optimization procedure, which is a list with the following elements:

- `estimate` is the parameter vector at termination.
- `value` is the function value at termination.
- `details` is a `data.frame` with full information about the procedure: For each iteration (column `iteration`) it contains the function value (column `value`), parameter values (columns starting with `p` followed by the parameter index), the active parameter block (columns starting with `b` followed by the parameter index, where 1 stands for a parameter contained in the active parameter block and 0 if not), computation times in seconds (column `seconds`), and a code that summarizes whether the update got accepted (column `update_code`, where 0 stands for an accepted update, 1 for a rejected update due to an error when solving the sub-problem, and 2 for a rejected update because it did not improve the function value).
- `seconds` is the overall computation time in seconds.
- `stopping_reason` is a message why the procedure has terminated.

Methods

Public methods:

- `Procedure$new()`
- `Procedure$print_status()`

- `Procedure$initialize_details()`
- `Procedure$update_details()`
- `Procedure$get_partition()`
- `Procedure$get_details()`
- `Procedure$get_value()`
- `Procedure$get_value_latest()`
- `Procedure$get_parameter()`
- `Procedure$get_parameter_latest()`
- `Procedure$get_seconds()`
- `Procedure$get_seconds_total()`
- `Procedure$check_stopping()`

Method `new()`: Creates a new object of this R6 class.

Usage:

```
Procedure$new(
  npar = integer(),
  partition = "sequential",
  new_block_probability = 0.3,
  minimum_block_number = 2,
  verbose = FALSE,
  minimize = TRUE,
  iteration_limit = Inf,
  seconds_limit = Inf,
  tolerance_value = 1e-06,
  tolerance_parameter = 1e-06,
  tolerance_parameter_norm = function(x, y) sqrt(sum((x - y)^2))
)
```

Arguments:

`npar` (integer(1))

The (total) length of the target argument(s).

`partition` (character(1) or list())

Defines the parameter partition, and can be either

- "sequential" for treating each parameter separately,
- "random" for a random partition in each iteration,
- "none" for no partition (which is equivalent to joint optimization),
- or a list of vectors of parameter indices, specifying a custom partition for the alternating optimization process.

`new_block_probability` (numeric(1))

Only relevant if `partition = "random"`. The probability for a new parameter block when creating a random partitions. Values close to 0 result in larger parameter blocks, values close to 1 result in smaller parameter blocks.

`minimum_block_number` (integer(1))

Only relevant if `partition = "random"`. The minimum number of blocks in random partitions.

verbose (logical(1))
 Whether to print tracing details during the alternating optimization process.

minimize (logical(1))
 Whether to minimize during the alternating optimization process. If FALSE, maximization is performed.

iteration_limit (integer(1) or Inf)
 The maximum number of iterations through the parameter partition before the alternating optimization process is terminated. Can also be Inf for no iteration limit.

seconds_limit (numeric(1))
 The time limit in seconds before the alternating optimization process is terminated. Can also be Inf for no time limit. Note that this stopping criteria is only checked *after* a sub-problem is solved and not *within* solving a sub-problem, so the actual process time can exceed this limit.

tolerance_value (numeric(1))
 A non-negative tolerance value. The alternating optimization terminates if the absolute difference between the current function value and the one from the last iteration is smaller than tolerance_value. Can be 0 for no value threshold.

tolerance_parameter (numeric(1))
 A non-negative tolerance value. The alternating optimization terminates if the distance between the current estimate and the one from the last iteration is smaller than tolerance_parameter. Can be 0 for no parameter threshold. By default, the distance is measured using the euclidean norm, but another norm can be specified via the tolerance_parameter_norm field.

tolerance_parameter_norm (function)
 The norm that measures the distance between the current estimate and the one from the last iteration. If the distance is smaller than tolerance_parameter, the procedure is terminated. It must be of the form function(x, y) for two vector inputs x and y, and return a single numeric value. By default, the euclidean norm function(x, y) sqrt(sum((x - y)^2)) is used.

Method `print_status()`: Prints a status message.

Usage:

```
Procedure$print_status(message, message_type = 8, verbose = self$verbose)
```

Arguments:

message (character(1))

The status message.

message_type (integer(1))

The type of the message, one of the following:

- 1 for `cli::cli_h1()`
- 2 for `cli::cli_h2()`
- 3 for `cli::cli_h3()`
- 4 for `cli::cli_alert_success()`
- 5 for `cli::cli_alert_info()`
- 6 for `cli::cli_alert_warning()`
- 7 for `cli::cli_alert_danger()`
- 8 for `cli::cat_line()`

`verbose (logical(1))`

Whether to print tracing details during the alternating optimization process.

Method `initialize_details()`: Initializes the details part of the output.

Usage:

`Procedure$initialize_details(initial_parameter, initial_value)`

Arguments:

`initial_parameter (numeric())`

The starting parameter values for the procedure.

`initial_value (numeric(1))`

The function value at the initial parameters.

Method `update_details()`: Updates the details part of the output.

Usage:

`Procedure$update_details(`

`value,`

`parameter_block,`

`seconds,`

`error,`

`block = self$block`

`)`

Arguments:

`value (numeric(1))`

The updated function value.

`parameter_block (numeric())`

The updated parameter values for the active parameter block.

`seconds (numeric(1))`

The time in seconds for solving the sub-problem.

`error (logical(1))`

Whether solving the sub-problem resulted in an error.

`block (integer())`

The currently active parameter block, represented as parameter indices.

Method `get_partition()`: Get a parameter partition.

Usage:

`Procedure$get_partition()`

Method `get_details()`: Get the details part of the output.

Usage:

`Procedure$get_details(`

`which_iteration = NULL,`

`which_block = NULL,`

`which_column = c("iteration", "value", "parameter", "block", "seconds", "update_code")`

`)`

Arguments:

```

which_iteration (integer())
  Selects the iteration(s). Can also be NULL to select all iterations.

which_block (character(1) or integer())
  Selects the parameter block in the partition and can be one of
  • "first" for the first parameter block,
  • "last" for the last parameter block,
  • an integer vector of parameter indices,
  • or NULL for all parameter blocks.

which_column (character())
  Selects the columns in the details part of the output and can be one or more of "iteration",
  "value", "parameter", "block", "seconds", and "update_code".

```

Method `get_value()`: Get the function value in different steps of the alternating optimization procedure.

Usage:

```

Procedure$get_value(
  which_iteration = NULL,
  which_block = NULL,
  keep_iteration_column = FALSE,
  keep_block_columns = FALSE
)

```

Arguments:

```

which_iteration (integer())
  Selects the iteration(s). Can also be NULL to select all iterations.

which_block (character(1) or integer())
  Selects the parameter block in the partition and can be one of
  • "first" for the first parameter block,
  • "last" for the last parameter block,
  • an integer vector of parameter indices,
  • or NULL for all parameter blocks.

keep_iteration_column (logical())
  Whether to keep the column containing the information about the iteration in the output.

keep_block_columns (logical())
  Whether to keep the column containing the information about the active parameter block in
  the output.

```

Method `get_value_latest()`: Get the function value in the latest step of the alternating optimization procedure.

Usage:

```
Procedure$get_value_latest()
```

Method `get_parameter()`: Get the parameter values in different steps of the alternating optimization procedure.

Usage:

```
Procedure$get_parameter(
  which_iteration = self$iteration,
  which_block = NULL,
  keep_iteration_column = FALSE,
  keep_block_columns = FALSE
)
```

Arguments:

`which_iteration` (integer())

Selects the iteration(s). Can also be NULL to select all iterations.

`which_block` (character(1) or integer())

Selects the parameter block in the partition and can be one of

- "first" for the first parameter block,
- "last" for the last parameter block,
- an integer vector of parameter indices,
- or NULL for all parameter blocks.

`keep_iteration_column` (logical())

Whether to keep the column containing the information about the iteration in the output.

`keep_block_columns` (logical())

Whether to keep the column containing the information about the active parameter block in the output.

Method `get_parameter_latest()`: Get the parameter value in the latest step of the alternating optimization procedure.

Usage:

```
Procedure$get_parameter_latest(parameter_type = "full")
```

Arguments:

`parameter_type` (character(1))

Can be one of

- "full" (default) to get the full parameter vector,
- "block" to get the parameter values for the current block, i.e., the parameters with the indices `self$block`
- "fixed" to get the parameter values which are currently fixed, i.e., all except for those with the indices `self$block`

Method `get_seconds()`: Get the optimization time in seconds in different steps of the alternating optimization procedure.

Usage:

```
Procedure$get_seconds(
  which_iteration = NULL,
  which_block = NULL,
  keep_iteration_column = FALSE,
  keep_block_columns = FALSE
)
```

Arguments:

```
which_iteration (integer())
    Selects the iteration(s). Can also be NULL to select all iterations.
which_block (character(1) or integer())
    Selects the parameter block in the partition and can be one of
    • "first" for the first parameter block,
    • "last" for the last parameter block,
    • an integer vector of parameter indices,
    • or NULL for all parameter blocks.
keep_iteration_column (logical())
    Whether to keep the column containing the information about the iteration in the output.
keep_block_columns (logical())
    Whether to keep the column containing the information about the active parameter block in
    the output.
```

Method `get_seconds_total()`: Get the total optimization time in seconds of the alternating optimization procedure.

Usage:

```
Procedure$get_seconds_total()
```

Method `check_stopping()`: Checks if the alternating optimization procedure can be terminated.

Usage:

```
Procedure$check_stopping()
```

Index

ao, [2, 5](#)

ao_input_check, [5](#)

optim, [4](#)

Optimizer, [4](#)

Procedure, [6](#)

R6, [8](#)